



**Mondial
Relay**



InPost

PERMALINKS

Version : 2.1

Date : Octobre 2017




Updates

Version	Date	Comments
V-1	August 2010	Document creation
V-1.1	February 2011	Update
V-1.2	August 2011	Reviewed list and corections
V-1.2	January 2011	English translation
V-1.3	July 2013	Tracing language code adding
V-1.4	March 2013	Map cancellation
V-1.5	October 2014	CRC Permalink cancellation
V-2	July 2015	Update
V-2.1	October 2017	New languages

Contents

- Introduction..... 4
- Terms..... 5
 - Tracking 5
 - Regular expressions..... 5
 - ISO standard 5
- General specifications of exchanges 6
 - General description 6
 - Regularity of calls 6
 - Choice of default language and country 6
 - Debug mode 6
- Tracking display 7
 - Basic URL of the page 7
 - In parameters 7
 - Example 7





Introduction

This document is designed to define the operation of the links with the different Mondial Relay™ website pages with the aim to search / list / post one or several Point Relais® or to post shipment information or its tracking.

Terms

Tracking

The tracking is the information given to obtain the shipment status at a specific time. The tracking usually indicates the date, the location and the treatment done to a parcel in a shipment.

Regular expressions

A regular expression is a character strings.

The regular expressions are used today by IT people in publishing and text control as well as in formal language usage which are part of the IT languages.

ISO standard

The document refers to two ISO standards in order to identify the countries and languages.

The reference standard for the country codes is ISO 3166-1. Only the code « alpha-2 » from this standard is used by par Mondial Relay.

For further information, please consult the following : https://en.wikipedia.org/wiki/ISO_3166-1

The reference standard for the language codes is ISO 639-1.

For further information, please consult the following : https://en.wikipedia.org/wiki/ISO_639-1

Mondial Relay is not responsible for the content of the above pages and cannot guarantee the information in them.

The Mondial Relay™ website doesn't include all countries and language codes present in the ISO standards mentioned above.

To obtain the list of allowed countries and languages, please inquire at Mondial Relay™.

NB : We manage Monaco with the FR ISO Country Code

General specifications of exchanges

General description

The following section describes the main functions to enable the link between the Mondial Relay™ website and the Merchant's website. All Mondial Relay™ websites allow the usage of functions stated in this document, however we recommend using this URL:

<https://www.mondialrelay.com>

All calls to different pages will be secured by a control key.

The calculation algorithm of the control key will be discussed further on.

Regularity of calls

In normal use, the different functions described in this document mustn't be called in « batch » form.

Meaning the requests must be spread out during the day and night according to the requests from the end users. (Points Relais® research, orders, etc ...). This use mode « in real time » is necessary not to disturb the others web users by saturating the server resources.

Choice of default language and country

All pages have 2 parameters to select the language and country selected on the web site.

In case one is missing or the second or both, some default values are given according to page domain name.

Thus, for a call from www.mondialrelay.fr, the language is French and the country is France. We strongly recommend setting a default values for www.mondialrelay.com because neither language, nor country is definitely established for this URL.

The parameters must be sent to the URL with the « get » method.

The parameter enable to modify the language is « language ».

The parameter enable to modify the country is « country ».

The values of these parameters meet the ISO standard as defined above in the document.

Debug mode

To facilitate error search during developments, we can use the « debug » parameter. This parameter must be sent with the « GET » method, in the page URL. The value of this parameter is digital and must be « 1 » to activate the mode.

Tracking display

This function enables to post the tracking result of shipment search.

Basic URL of the page

<https://www.mondialrelay.com/public/permanent/tracking.aspx>

In parameters

<i>Parameter</i>	Optional (F) Obligatory(O)	<i>Format</i>
ens	O	10 fix characters
This parameter is a unique id for each Merchant.		$^{[0-9A-Z]{2}[0-9A-Z_]{6}[0-9]{2}}\$$
exp	O	8 fix digital characters
Shipment number		$^{[0-9]{8}}\$$
language	F	2 fix characters
ISO language code (ISO 639-1)		Code ISO, pour le français : FR $^{[A-Z]{2}}\$$ Allowed languages : FR, DE, NL, IT, EN, ES, PT

Example

<https://www.mondialrelay.com/public/permanent/tracking.aspx?ens=BDTEST1211&exp=17185966&language=FR>

This link is given as an example and could possibly not work.



4/25/2016	
3:55 PM	DELIVERED PARCEL
Your package has been delivered	
4/21/2016	
10:32 AM	PARCEL AVAILABLE AT THE POINT RELAIS (PICKUP POINT)
HAPPY SISYPHE 20 PLACE CARNOT 69002 - LYON FR	6:15 AM
SHOW DETAILS	
PARCEL DELIVERED TO THE DELIVERYMAN	
4:41 AM	PARCEL TAKEN OVER BY AGENCY LYON
4:40 AM	PARCEL TAKEN OVER BY AGENCY LYON
4/20/2016	
1:58 PM	PARCEL TAKEN OVER BY AGENCY HEM_US
1:56 PM	PARCEL TAKEN OVER BY OUR NETWORK
AGENCE MONDIAL RELAY 9 AVENUE ANTOINE PINAY 59510 - HEM FR	
SHOW DETAILS	